


How to use Survey Stop Actions

How to use Survey Stop Actions

The Stop Survey action will prompt the survey participant to end the survey when a specific answer is given. The stop survey action is available on **Drop-down List, Radio Buttons, Multiple Answers, Yes/No, and True/False** field types.

Once you have created one of the field types listed above and you have your data collection instrument set up as a survey, you will see a **Stop Sign** icon.




A screenshot of a survey question editor. At the top, there is a toolbar with icons for edit, copy, paste, add, and a red stop sign icon. The stop sign icon is highlighted with a red arrow. To the right of the toolbar, it says "Variable: agree_to_participate". Below the toolbar, the question text is "Do you agree to participate in this study?" and there are two radio button options: "Yes" and "No".

To add the Stop Survey logic, click on the **Stop Sign** icon. The Stop Survey logic box will appear. Select the answer choice that should prompt the survey participant to end the survey and click Save.


Example

In this example, I want the survey participant to be prompted when they click No.



A screenshot of the "Set up Stop Actions for this Survey Question" dialog box. The title bar says "Set up Stop Actions for this Survey Question" with a close button. Below the title bar, there is a red stop sign icon and the text "Stop Actions (for survey questions only):". The text below explains that the survey participant will be prompted to end the survey when ANY choices checked below are selected for this question on the survey. It also notes that Stop Actions will not be enabled on the form when viewing in REDCap as an authenticated user, but only become enabled when a participant views this data collection instrument as a survey. Below this text, there is a preview of the survey question: "Do you agree to participate in this study?" with two radio button options: "Yes" and "No". The "No" option is checked. To the right of the preview, there are links for "Select All" and "Deselect All". At the bottom of the dialog, there are "Save" and "Close" buttons.

Notice that once the Stop Survey logic is set up, the text appears next to the answer choice that will end the survey.



A screenshot of the survey question editor after the Stop Survey logic is set up. The toolbar at the top is the same as in the previous screenshot. The question text is "Do you agree to participate in this study?". The "Yes" radio button is unselected, and the "No" radio button is selected. Next to the "No" radio button, the text "[End Survey]" is displayed in red.

When the participant takes the survey and they answer No, they will receive the following message. The message is hardcoded and cannot be changed. The participant can either choose to "End the survey now" which would take them to the Survey Acknowledgment text or they can choose "Continue survey and undo last response".

End the survey?



You have selected an option that triggers this survey to end right now. To save your responses and end the survey, click the button below to do so. If you have selected the wrong option by accident and do not wish to leave the survey, you may click the other button below to continue, which will also remove the value of the option you just selected to allow you to enter it again and continue the survey.

End the survey now

Continue survey and undo last response